


Application: Snap-on EPC 5

DMS: R&R ERA Ignite


Configuring Snap-on EPC 5 for Integration

- 1. The **Integration Assistant** is seamlessly integrated into EPC 5, streamlining the setup of the integration you need.
 - A. Click on **Settings** and select the **Integration Settings Menu**
 - B. Click on New
 - C. Select "File Writer" from the Type drop-down menu.




- 2. Configure Integration within Snap-on EPC 5.
 - A. In the **Name** field, enter a descriptive name for the integration, preferably one that identifies the system you're integrating with. For instance, we'll use "IGNITE."






B. In the File format field, select STARDTS17 to set the file format.




C. The **File name** and **File folder** fields are pre-filled with a default name and location. Click the **Next** button.




- 3. Finish Integration Setup.
 - A. On the next screen, select your **manufacturer** and choose the **part number format**. Then, click **Next**.





- B. On the next screen you have two options:
 - Select "Everyone in my dealership" if you want all users on a server system or web application to see the same Integration Session. (NOTE: With this option, If IPS is already installed you don't need to set up Integration on other PCs—they will already be listed.)
 - Select "Just Me" if you're using a standalone system or want the Integration Setup to apply only to your PC or username.
 - After making your selection, click **Next** then **Finish**.





C. You should now see the newly created integration listed in your **Configured Integrations** screen. Click the "X" in the upper right corner to exit.

Workflow

- 1. Adding and Sending Parts using Snap-on EPC 5.
 - A. Find the required part number in EPC.
 - B. Left click the **plus symbol** to the left of the part number you wish to select.
 - This will place a check in that box.
 - The selected part will appear in the **Picklist** at the bottom of EPC 5. (**NOTE**: You may need to hit the maximize button then minimize button to view the Picklist)
- 2. Removing Parts from Snap-on EPC 5 Picklist
 - A. Click the **minus symbol** next to an individual part number to remove one item at a time from the Picklist.



- B. Click the **Clear button** clear to delete the entire Picklist.
- 3. Transferring Part Numbers into ERA Ignite from Snap-on EPC 5
 - A. Open **ERA Ignite** and log into the DMS system.
 - B. In the EPC 5 Picklist, the **Send To:** drop-down should show **IGNITE**.



- C. Click the **Send to Selected Integration** button in the Picklist to send parts to ERA Ignite.
 - Behind the scenes, all parts listed in the Picklist will also be automatically written to the file you designated on your PC in section 2-C above.
- D. Transfer Part Number(s) to ERA Ignite.
 - Make sure you're at the Part Number prompt in ER Ignite (see illustration below).
 - To add a Part Number to ERA Ignite, go to Functions→Import
 Catalog Parts or use Ctrl-G to initiate the part(s) transfer into
 the DMS.

